

## API CALLS

### LIST OF ALL PLAYOUTS

[Playouts/short](#)

Main Playouts				
PLAYOUT	△ CHANNEL	STATUS	PLAYING	SPARE
I9 PC 2		OFFLINE	<span>● Stopped</span>	
I9 ULTIMATE	JB1	ON AIR	<span>● Stopped</span>	
I9 ULTIMATE 2	JB2	OFFLINE	<span>● Stopped</span>	
I9 ULTIMATE 3	JB3	OFFLINE	<span>● Stopped</span>	
I9 ULTIMATE 4	JB4	OFFLINE	<span>● Stopped</span>	
SPARE DRUGI PC		OFFLINE	<span>● Stopped</span>	
SPARE I9		OFFLINE	<span>● Stopped</span>	✓

Returns PlayoutListInfo. Now I used Binding List for this, not sure if you can use it for DevExpress grid, but anyway here are both options

```
public class PlayoutListInfo
```

Or if you only want to use class, without notifications

```
public class PlayoutListInfo2
```

For Status column, possible values are

```
"0", "OFFLINE"  
"1", "ON AIR"  
"2", "UNKNOWN"
```

Color for "2" should be some dark yellow, I used 122, 95, 32

For Playing column, possible values are

```
"0", "Stopped"  
"1", "Playing"
```

You can use as it is in Figma, Green = playing, Blue = stopped. Picture I sent up is desktop version, you do as it is in Figma

Once playouts are loaded, we send request via SignalR to all apps to send their status.



Playouts text is fixed. Number in the middle get from this same api call. For text below, I used this method

```
internal string ReturnLayoutStatusNo()
{
    int spare = Playouts.Where(p => p.Spare).Count();

    return Playouts.Where(p => !p.Spare && p.IsOnline == 1).Count().ToString() + "running, " + Playouts.Where(p => !p.Spare && p.isPlaying == 1).Count().ToString() + "playing" + (spare > 0 ? ", " + spare.ToString() + " spare" : string.Empty);
}

Playouts is List<PlayoutListInfo>
```

SignalR

Endpoint is [/broadcastHub](#)

Id for signalR is random GUID

Group for signalR is “WebDashboard”

```
await _connection.InvokeAsync("RegisterClient", clientId, group);
```

Connection uses JWT from login.

And from desktop apps, I do Ping on server every 5 seconds

We have 2 events

```
_signalR.CommandReceived += OnCommandReceived;
_signalR.ConnectionStateChanged += OnConnectionStateChanged;
```

OnConnectionStateChanged

```
switch (obj)
{
    case "Connected":
        foreach (var playout in playoutControl1.Playouts)
        {
            playout.IsOnline = 0;
        }
        break;
    case "Closed":
        foreach (var playout in playoutControl1.Playouts)
        {
            playout.IsOnline = 2; //set Unknown status when there is no connection
        }
}
```

```

        break;
}

```

We use `CommandDto` to send via SignalR.

So after layouts are loaded, we send this command to signalR to ask all apps about their status. Probably I will upgrade this to send only to Playouts (I can change this later)

```

public async Task SendRequest(string ClientId)
{
    if (_connection == null)
        return;

    if (_connection.State == HubConnectionState.Connected)
    {
        try
        {
            await _connection.InvokeAsync("SendToAllExcept", ClientId, new
CommandDto
            {
                command = ServiceMessages.RequestStatusSync.ToSignal(),
                clientId = ClientId
            });
        }
        catch (Exception ex)
        {
            // može i logger
            Console.WriteLine("Ping error: " + ex.Message);
        }
    }
}

```

#### OnCommandReceived

And in `OnCommandReceive`, we get status of apps like this

```

private async void OnCommandReceived(object data)
{
    if (InvokeRequired)
    {
        try
        {
            Invoke(new System.Action(() => OnCommandReceived(data)));
        }
        catch { }
        return;
    }

    CommandDto? comm = data.ToObject<CommandDto>();

    if (comm != null)
    {

```

```

switch (comm.command.FromSignal<ServiceMessages>())
{
    case ServiceMessages.ClientStatusChanged:
        if (comm.group != null && comm.group.Length > 0)
        {
            switch (comm.group.FromSignal<ClientType>())
            {
                case ClientType.PlayoutServer:
                    playoutControl1.PlayoutStatusChanged(comm);
                    GetPlayoutNo();
                    break;
                case ClientType.RemoteControl:
                case ClientType.Scheduler:
                case ClientType.CgControl:
                    onlineControl1.SetStatus(comm);
                    break;
            }
        }
        break;
}

```

PlayoutStatusChanged just update Status (isOnline value), and change status from Offline to On Air.

For Playing column, we will do that later, when playout is finished, so what you can do for test is to change that value also in PlayoutStatusChanged (when playout is online, it's also playing, when it's offline, then it's stopped)

SignalR Interface, if you need it

```

Task RegisterClientAsync(string clientId, string clientType, string connectionId,
string userid, string username, string name);
Task HandleDisconnectAsync(string connectionId);
Task UpdatePingAsync(string clientId);

Task<string> NotifyClientStatusAsync(string clientId, string clientType, string
userid, string username, string name, string status);
Task NotifyEntityChangedAsync(object data);

Task<string> SendToClientAsync(string clientId, object data);
Task<string> SendToGroupAsync(string groupName, object data, string
exceptConnectionId, bool except);
Task<string> SendToGroupsAsync(IEnumerable<string> groupNames, object data);
Task SendToAllAsync(object data);
Task SendToAllExceptAsync(string id, object data);
Task<IReadOnlyCollection<ClientSession>> GetClientsSnapshot();

// Maps and tracking
ConcurrentDictionary<string, string> ClientConnections { get; }
ConcurrentDictionary<string, ClientSession> AllClients { get; }
ConcurrentDictionary<string, DateTime> LastPing { get; }
Dictionary<string, HashSet<string>> GroupsMap { get; }

```